

# Configurazioni client di posta

- Configurazioni generali di posta
- Mail General Configurations
- Configurazione iPhone (IMAP)
- iPhone configuration (IMAP)

# Configurazioni generali di posta

Salvo che diversamente indicato, questi sono i parametri per configurare i programmi di posta per le proprie caselle di posta ospitate sui server di [WhiteReady](#).

Forniamo i servizi di posta sia su protocollo IMAP4 che POP3.

Forniamo inoltre il servizio SMTP e, nel caso di necessità di **invii massivi di mail**, anche un servizio SMTP Bulk.

<b>IMAP4</b>	
Nome del server	<b>imap.whiteready.com</b>
Nome utente	l'indirizzo email completo ( <a href="#">mario.rossi@dominio.tld</a> )
Password	la password assegnata
Porta	<b>143</b> (senza SSL)
	<b>993</b> (con SSL)
<b>POP3</b>	
Nome del server	<b>pop.whiteready.com</b>
Nome utente	l'indirizzo email completo ( <a href="#">mario.rossi@dominio.tld</a> )
Password	la password assegnata
Porta	<b>110</b> (senza SSL)
	<b>995</b> (con SSL)

## SMTP

Nome del server	<b>smtp.whiteready.com</b>
Nome utente	l'indirizzo email completo ( <b>mario.rossi@dominio.tld</b> )
Password	la password assegnata
Porta	<b>25</b> (senza SSL)
	<b>587</b> (con STARTTLS)
	<b>465</b> (con SSL/TLS)

Per l'SMTP Bulk contattare direttamente [WhiteReady](#).

Le caselle di posta fornite da [WhiteReady](#) sono, salvo casi particolari, autoconfiguranti: utilizzando le versioni più aggiornate dei normali programmi di posta come [Thunderbird](#) o [Outlook](#) è sufficiente inserire l'indirizzo email e la password: il sistema provvederà automaticamente a completare l'intera configurazione.

È inoltre disponibile la [webmail](#), raggiungibile all'indirizzo <https://indirizzofacile.it>, a cui si accede con le medesime credenziali. La webmail si comporta come un normale programma di posta configurato in IMAP.

Dalla [webmail](#) l'utente può, in autonomia, agire su alcune impostazioni, fra cui:

- cambiare la password della propria casella
- impostare un messaggio automatico di "Out of office"
- impostare un inoltro
- gestire le policy antispam
- gestire le cartelle IMAP sottoscritte
- impostare filtri
- ...

# Mail General Configurations

Unless otherwise indicated, these are the parameters for configuring mail programs for your mailboxes hosted on WhiteReady's servers.

We provide mail services on both IMAP4 and POP3 protocols.

We also provide the SMTP service and, in case of need for mass mailings, also a Bulk SMTP service.

<b>IMAP4</b>	
Name server	<b>imap.whiteready.com</b>
User name	Your full email address (smith@domain.com)
Password	Password
Port	<b>143</b> (NO SSL)
	<b>993</b> (YES SSL)
<b>POP3</b>	
Name server	<b>pop.whiteready.com</b>
User name	Your full email address (smith@domain.com)
Password	Password
Port	<b>110</b> (NO SSL)
	<b>995</b> (YES SSL)
<b>SMTP</b>	
Name server	<b>smtp.whiteready.com</b>

User name	Your full email address (smith@domain.com)
Password	Password
Port	<b>25</b> o <b>587</b> (NO SSL)
	<b>465</b> (YES SSL)

For the Bulk SMTP please contact [WhiteReady](#).

The mailboxes provided by [WhiteReady](#) are, except in special cases, self-configuring: using the most updated versions of normal mail programs such as [Thunderbird](#) or [Outlook](#) it is sufficient to enter the email address and password: the system will automatically complete the entire configuration .


The webmail is also available, reachable at the address <https://indirizzofacile.it>, which can be accessed with the same credentials. The webmail is like a normal mail program configured in IMAP.

From the [webmail](#) the user can autonomously adjust some settings, including:


- change your mailbox password
- set an automatic "Out of office" message
- set up a forward
- manage spam policies
- manage subscribed IMAP folders
- set filters
- ...

# Configurazione iPhone (IMAP)


Clicca sulle impostazioni, quindi su "Mail"



Cliccare su "Accounts"




Clicca su "Aggiungi account"




Clicca su "Altro"





Clicca su "Aggiungi account di posta"



Inserisci il tuo nome, l'indirizzo email che vuoi configurare e la password, quindi cliccare su "Avanti", in alto a destra

14:08

Cancel New Account Next

Name John Appleseed

Email user@example.com

Password Required

Description My Email Account

Completare tutti i campi richiesti: l'indirizzo email che si vuole configurare, il nome del server della posta in entrate (che è **imap.whiteready.com**), il nome utente e la password.

Fare lo stesso sul server di posta in uscita (che è **smtp.whiteready.com**), inserendo di nuovo il nome utente e la password

13:49

Cancel New Account Next

Email [REDACTED]

Description [REDACTED]

INCOMING MAIL SERVER

Host Name imap.whiteready.com

Username [REDACTED]

Password

OUTGOING MAIL SERVER

Host Name smtp.whiteready.com

Username [REDACTED]

Password

Passwords

q w e r t y u i o p

a s d f g h j k l

↑ z x c v b n m ↵

123 😊 space return


🌐 🎤

Salvare la configurazione cliccando su "Avanti" in alto a destra.




# iPhone configuration (IMAP)


Tap on "**Settings**", then on "**Mail**"



Tap on "**Accounts**"




Tap on "**Add Account**"




Tap on **"Other"**





Tap on "Add Mail Account"



Insert your name, the email address you want to configure and password, then tap on "**Next**", at right top corner

14:08

Cancel New Account Next

Name John Appleseed

Email user@example.com

Password Required

Description My Email Account

Complete all fields: the email address you want to configure, the incoming mail server (**imap.whiteready.com**), username and password.

Do the same on the outgoing mail server (which is **smtp.whiteready.com**), again entering the username and password

13:49

Cancel New Account Next

Email [REDACTED]

Description [REDACTED]

INCOMING MAIL SERVER

Host Name imap.whiteready.com

Username [REDACTED]

Password

OUTGOING MAIL SERVER

Host Name smtp.whiteready.com

Username [REDACTED]

Password

Passwords

q w e r t y u i o p

a s d f g h j k l

↑ z x c v b n m ↵

123 😊 space return


🌐 🎤

Save configurazione with tap on "**Next**", at right top corner.


## Other settings

### Outgoing mail server

Tap on "**Outgoing mail server**" -> **SMTP**, then tap on "**PRIMARY SERVER**"




Set hostname (smtp.whiteready.com), username (the same of incoming mail server) and the password, set "On" the SSL flag, check if Server Port is 665.



Tap on "Done", on the right top corner.

At the bottom of this page, you see another button: "**Advanced**". Tap on.

## Account settings Advanced



The part that interests us is the one marked in red

Set '**Use SSL**' to 'Active'.

Check that the server port is **993**.

